

# TIS (TheImagingSource) USB camera installation



First, check that your Windows system and drivers are up to date, especially USB, Chipset and graphics card.

You must have 'Administrator' rights


Do not connect the camera until you have installed the TIS drivers.

Insert the USB stick and follow the instructions below.


Installation of TIS camera drivers.



Run the file  
'Cam33U\_setup\_5.1.0.1719.exe'  
(the file may be different!)



1




2


## Installation of the TIS ICCapture program




Run the file  
'setup\_iccapture\_2.5.1547.4007.en\_US.exe'  
(the file may be different!)




1



The installation is complete. 2



The ICCapture application runs  
(if Launch IC Capture is checked).  
Now connect the camera.



The camera image should now appear,  
after quitting everything, the applications using  
these cameras will work correctly.

USB3 cameras must be plugged into a USB3 port,  
normally blue in colour or marked 'SS' (Super Speed).